Treatment Planner (BETA)

A conservation strategy tool designed to help prioritize forest management actions by connecting ArcGIS, FVS, and EEMS within a 4-Box decision making framework.

User Manual Version 0.0.2





Table of Contents

I. INTRODUCTION	4
1.1 Purpose and Contents	4
1.2 Software Requirements	5
1.3 Data Requirements	6
1.4 Recommended Training & Experience	6
II. OVERVIEW	7
2.1 What is the 4-Box Model?	7
2.2 What is the Treatment Planner?	8
III GETTING STARTED	9
3.1 The Treatment Planner Contents	9
3.2 The Treatment Planner Toolbox	10
IV. TREATMENT PLANNER TUTORIAL	15
4.1 Overview	15
4.2 Disclaimer	15
4.3 Preparation	16
4.4 Scenario 1: No Action Alternative	18
4.5 Scenario 2: Single Thinning Treatment	20
4.6 Conclusion	22
V. ADDING CUSTOM EEMS MODELS	23
REFERENCES CITED	26

Note: The Treatment Planner is currently available as a beta version. At the time of this writing, the project is seeking funding to take the next steps toward fully implementing the software. We welcome feedback-- if you have questions, comments, or encounter any problems, please contact the Conservation Biology Institute at geospatial@consbio.org.

I. INTRODUCTION

1.1 Purpose and Contents

The Treatment Planner software program was developed to provide land and forest managers a platform for exploring the potential consequences of different forest management alternatives in both the short and long-term, examine the resource-based trade-offs inherent in any proposed vegetation management action, and clearly substantiate the rationale behind management planning. Originally envisioned as a means to help balance fisher habitat conservation with fuel reduction efforts, the Treatment Planner provides a dynamic link between GIS, the Forest Vegetation Simulator (FVS, https://www.fs.fed.us/fvs/) modeling software, and any resource model (e.g. habitat, hydrology, fuel, economic) that can be portrayed in the EEMS modeling environment. As such, the Treatment Planner is not a model per-se, but a system of communication between existing software platforms that can facilitate spatially-explicit comparisons and project refinement.

The Treatment Planner supports an iterative process of treatment project simulation, adaptive management, and outcomes analysis, the steps in what we refer to as the "4-Box" decision making framework, described in more detail in Section II. Under this framework, managers can simulate the potential future outcomes of a given management scenario on a particular resource. They can project these outcomes into the future to better understand long-term consequences, explore modifications to the proposed treatment that may mitigate any undesirable effects, and compare the outcomes of different alternatives. By exporting an FVS model output directly into the EEMS modeling environment, the framework allows for a transparent evaluation of the impacts to multiple resource values and a straight-forward process for communicating these impacts to stakeholders.

The purpose of this document is to provide instruction and guidance on the use of the beta version of the Treatment Planner. Upon successful completion of this document, readers should be able to:

- 1. Understand the relationship between the 4-Box model and the Treatment Planner.
- 2. Effectively use the Treatment Planner to help inform their forest management decisions.

How this document is organized

Section I describes the software, technical, and data requirements needed to get started using the Treatment Planner. Section II provides a conceptual overview of the 4-Box model that forms the core of the Treatment Planner. Section III provides a step-by-step tutorial on how to use the Treatment Planner. And finally, Section IV describes how users can add their own EEMS models to the Treatment Planner.

1.2 Software Requirements

The Treatment Planner is not a stand-alone desktop application. Rather it forms a bridge between three different software packages. Consequently, users will first need to ensure that they meet the software requirements listed below and have downloaded/installed any remaining programs that haven't already been installed.

1. Microsoft Windows 7 or Windows 10

2. ArcGIS Desktop 10.6.1 or greater

While earlier versions of ArcGIS may work, they have not been tested. ArcGIS Pro is currently not supported.

3. MPilot

MPilot is a plugin-based environmental modeling framework written in python. It is required in order to run EEMS Models developed using EEMS for ArcGIS.

To install MPilot, follow the instructions below:

- a. Open a command prompt (in Windows 10, you can do this by typing "cmd" into the Search box in the bottom left hand corner of your screen).
- b. Type in "cd C:\Python27\ArcGIS10.X\Scripts", replacing "X" with the version of ArcGIS Desktop you have installed.
- c. Type in "pip install mpilot".
- d. Restart ArcCatalog & ArcMap.

For more information regarding MPilot, visit the MPilot repository on GitHub:

https://github.com/consbio/mpilot

4. Forest Vegetation Simulator (FVS)

FVS (Seymour, Robert. (2013) *is a US Forest Service tool designed to simulate forest vegetation change in response to natural succession, disturbances, and management actions. You can download FVS at the URL below:*

https://www.fs.fed.us/fvs

5. Microsoft Access 2010 or greater

Microsoft Access is a relational database management system (RDBMS). It comes bundled with Microsoft Office Professional.

6. The Treatment Planner

The Treatment Planner is a Python Toolbox and does not need to be installed. The latest version can be downloaded from GitHub:

https://github.com/consbio/Treatment-Planner-BETA

7. EEMS for ArcGIS

EEMS is a fuzzy logic modeling system written in Python. The EEMS for ArcGIS toolbox is included with the Treatment Planner within the EEMS/EEMS3.1.0_ArcGIS folder. Since it is included, it does not need to be downloaded separately. Since it is a python toolbox, no installation is required. It is listed here solely for completeness. More information about EEMS can be found at the following URL:

https://consbio.org/products/tools/environmental-evaluation-modeling-system-eems

1.3 Data Requirements

1. An FVS Database

The Treatment Planner requires an existing FVS database to describe the current forest conditions. A sample database is included for use in the tutorial, but in order to use the Treatment Planner in a real-world setting, you will need an FVS database containing data for your study area. The FVS database must include, at a bare minimum, an FVS_StandInit table and an FVS_TreeInit table.

2. A "Stands" Feature Class

In addition to the FVS database, you will also need a shapefile or geodatabase feature class representing the stands in your FVS database. This feature class must have a STAND_ID field that can be linked to the STAND_ID field in the FVS database. A sample stands feature class is included with the Treatment Planner for use in the tutorial.

1.4 Recommended Training & Experience

- 1. In addition to the software and data requirements listed above, users should have formal GIS training and experience with ArcGIS Desktop and ArcGIS Model Builder.
- 2. Experience with EEMS and building EEMS models is also highly recommended as this will allow you to develop and connect your own EEMS models to the Treatment Planner.
- 3. Experience with Microsoft Access is recommended in order to be able to examine the FVS databases, but it is not required.

II. OVERVIEW

2.1 What is the 4-Box Model?

The 4-Box model is a conceptual representation of a process designed to help predict future landscape conditions based on simulated management actions and change over time (Figure 1). It was originally conceived of by Tim Sheehan, Ph. D., an ecological modeler and the original developer of <u>EEMS</u> (Sheehan, T. and Gough, M. (2016)). As illustrated below, the 4-Box model describes an iterative process whereby the land manager first examines the current conditions of the landscape through the lens of a particular question or management objective (e.g., *where are areas that need protection or restoration*?). They then engage in an exploratory process involving several "what-if" questions in order to examine the predicted effects of various simulated management alternatives. For example, if we were to perform one or more treatments on a forest stand (e.g., *thin from above, or thin from below*), how would that affect the stand structure over time (*e.g., how would it affect the stand density, basal area, and average DBH both immediately and into the future*)? And how would those new conditions then affect a particular phenomenon of interest (e.g., *severe fire risk, or wildlife habitat suitability*)? This process is then repeated under a different set of treatment options (scenarios) in order to help develop an effective management strategy to implement in the real world.



Figure 1. The 4-Box model represents a process for evaluating future conditions based on simulated treatments and change over time.

2.2 What is the Treatment Planner?

The 4-Box model is a conceptual framework for evaluating management scenarios and their resulting outcomes for a resource or landscape. The 4 boxes in the 4-Box model represent four evaluation steps that can be conducted in a repeating cycle as management planning progresses, incorporating previous management actions and new data about the resource or landscape to continue with a new planning cycle.

The 4 boxes (evaluation steps) are:

- **Define Treatments:** Description of proposed management actions in spatial data.
- **Examine Landscape Conditions**: Evaluation of conditions on the landscape to identify places that need management actions.
- **Evaluate a Phenomenon of Interest**: Analyze the landscape for attributes such as fire or drought resilience, or suitable habitat.
- **Simulate Change Over Time**: Model the future conditions with and without proposed management actions.

The 4-Box model could be implemented using a variety of different software packages and analytical techniques. The Treatment Planner is a software implementation of the 4-Box model that brings together all the components of the 4-Box model into a single tool with a user-friendly interface.

More specifically, the Treatment Planner is an ArcGIS script tool within a Python Toolbox. To run the tool, the user specifies several input parameters, which include:

- 1. The path to an existing FVS database which is used to define the current conditions of the landscape (*top box in the 4-Box model*).
- 2. A treatment or set of treatments to perform (*left box*).
- 3. The number of years to simulate forest growth/change (*bottom box*).
- 4. The phenomenon of interest to model based on the simulated future conditions (*right box*).

These input parameters are then handed off to the Forest Vegetation Simulator (FVS) to perform the specified treatment(s) and to simulate change over time. The outputs from FVS (e.g., trees per acre, basal area, etc.) are then handed off to the Environmental Evaluation Modeling System (EEMS) to model the phenomenon of interest (e.g., severe fire risk) based on these future conditions.

While a discussion of FVS and EEMS is beyond the scope of this document, users are encouraged to learn more about these applications at the URLs below:

FVS: https://www.fs.fed.us/fvs

EEMS: https://consbio.org/products/tools/environmental-evaluation-modeling-system-eems

The Treatment Planner comes with two built-in, draft EEMS Models to illustrate how the Planner can be used to evaluate phenomena of interest:

- Severe Fire Risk A simple model designed to evaluate the risk of severe fire occurrence under future conditions based on three terrain variables (Slope, Solar Insulation, and Southwestness) as well as four FVS-generated forest stand structure variables (Basal Area, Trees Per Acre, Stand Density Index, and Crown Competition).
- 2. **Thinning Assessment** A simple model to identify stands to prioritize for thinning treatments based on stand density, avoidance of old growth, and economic value.

These models can be used as-is, or tailored for a specific region or purpose. Additional EEMS models can be developed and added to the Treatment Planner by the user – the only requirement is that they are configured to make use of one or more of the outputs fields generated by FVS. A more thorough discussion of this topic is presented in section V (Adding Custom EEMS Models).

III GETTING STARTED

The Treatment Planner is distributed in a zip file that contains several files and folders (see Figure 2 below). To get started using the Treatment Planner, first extract the content of the zip file to a folder on your local hard drive. The items within the extracted folder must be maintained in their current locations within the existing directory structure. Moving these items around has the potential to cause problems.

3.1 The Treatment Planner Contents

- 1. A Data folder containing subfolders for Inputs, Intermediate, and Outputs.
- 2. A Docs folder containing this user manual
- 3. An EEMS folder containing EEMS as well as a set of sample EEMS Models (EEMS_Models.tbx)
- 4. An MXD folder for storing map documents (MXDs)
- 5. The Treatment Planner Toolbox (Treatment_Planner.pyt)



Figure 2. The Contents and directory structure of the Treatment Planner Download

3.2 The Treatment Planner Toolbox

The Treatment Planner Toolbox (Treatment_Planner.pyt) currently contains a single tool called "Run Simulation" (pictured below) which performs all the functions of the 4-Box model. Additional tools may be added in future versions.

3	Run Simulation		_		:	×
• F	Forest Stands Layer					~
					e3	
F	VS Database					
	F:\Projects2\USFS-052_PSW_Forest	_Treatment_Planner_2019_mike_gou	ugh\Tasks\FVS_Arc_4_Box_mode	et/te	2	
•	Number of Years to Simulate					
	Dutput Fields to Join (optional)					
	Stand Age				^	
	Trees per acre (Tpa)					
	Basal area per acre (BA)					
	Stand density index (Sdi)					
	Crown competition factor (CCF)					
	Average dominant height (TopHt Overlage DBH (OMD))				
	Quadratic mean DBH (QMD) Forest cover type (ForTyp)					
	Stand size class (SizeCls)				~	
	<			>		
	Select All Unselect All		Add	Value		
	Management Actions					
	Management Action(s) (optional)					
	Hanagement Action(5) (optional)				\sim	
	Action	Year	Advanced Settings (See Help)		÷	
					×	
					4	
					T	
					•	
	<			>		
	Run simulation on non-selected St	tands (optional)				
	Post-Processing Options					
	EEMS Model (optional)					
					\sim	
	EEMS Model Output Feature Class (op	otional)				
						\sim
		OK Can	el Environments Sh	iow He	lp >>	•

Figure 3. The Treatment Planner/Run Simulation Tool Interface

The tool input parameters are described in the table below. Note that these descriptions can also be accessed within the tool itself by simply placing your cursor in one of the input parameter fields and clicking the "Show Help" button.

Input Parameter	Description
Forest Stands Layer	The ArcGIS layer or feature class representing the stands in the FVS database. Must have a field called STAND_ID containing values that match those in the STAND_ID field of FVS_StandInit table.
FVS Database	The path to an FVS-ready database representing the forest stands and individual trees.
Number of Years to Simulate	The number of years to simulate forest vegetation growth/change into the future. A minimum of 1 year is required.
Output Fields to Join	The FVS outputs to join to the output stands feature class. Note that if you are running an EEMS model, you must check the boxes corresponding to those required by the READ commands in the EEMS model.
	Trees per acre (Tpa) is a count of the number of trees per acre.
	Basal area per acre (BA) describes the average amount of an acre (measured in square feet) occupied by the cross section of tree stems.
	Stand Density Index (Sdi) is a relative measure of stand density that is based on the number of trees per unit area and diameter at breast height (DBH) of the tree of average basal area (source: Wikipedia).
	Crown competition factor (CCF) (Krajicek and others 1961) is a relative measurement of stand density that is also based on tree diameters. Tree values of CCF estimate the percentage of an acre that would be covered by the tree's crown if the tree were open grown. Stand CCF is the summation of individual tree (CCFi) values. A value of 100 theoretically indicates that tree crowns will just touch in an unthinned, evenly spaced stand (source: FVS manual).
	Average dominant height (TopHt) is the average height of the 40 largest diameter trees (source: FVS Manual).
	Quadratic mean DBH (QMD) is the DBH of the tree of average basal area (source: FVS manual).
	Forest Cover Type (ForTyp) is a code representing the dominant forest type (lookup table here: https://www.fs.fed.us/fmsc/ftp/fvs/docs/bulletins/ForTyp_Codes.pdf)
	Stand size class (SizeCls) A code representing the following classes (FVS manual):

Table 1. The input parameters available in the Run Simulation tool.

	1 - Lourse (southinghout)
	1 = Large (sawtimber)
	2 = Medium (poletimber)
	3 = Small (seedling-sapling)
	4 = Chaparral/Woodland
	5 = Nonstocked
	Merchantable cuft volume (MCuFt) represents the volume of
	merchantable timber in cubic feet.
Treatment(s)/Management Action(s)	The treatments/management actions to perform on the selected stands. Select a management action from the dropdown menu, then enter in a year (starting at year 0) on which to perform that action, and (optionally) a CSV list for the <i>Advanced Settings</i> entered in the order specified below. If no stands are selected, the management action will be applied to all the stands. Note that the year field uses a 0 index starting value (so entering in a value of 0 would perform the treatment on the inventory
	year associated with the stand(s) in the FVS database).
	Thin from Above - (also known as French or crown thinning) the removal of trees from the dominant or codominant crown classes to favor the best trees of those same crown classes (source: FVS Tutorial).
	Advanced Settings:
	1. Trees per acre
	2. Proportion of trees left
	3. Diameter lower limits
	4. Diameter upper limits
	5. Height lower limits
	6. Height upper limits
	Thin from Below - (also known as ordinary, German, or low thinning) the removal of trees from the lower crown classes to favor those in the upper crown classes (source: FVS Tutorial).
	Advanced Settings:
	1. Trees per acre
	2. Proportion of trees left
	3. Diameter lower limits
	4. Diameter upper limits
	5. Height lower limits
	6. Height upper limits
	Clearcut - the cutting of essentially all trees, producing a fully exposed microclimate for the development of a new age class (source: FVS Tutorial).
	Tutorial).

	Advanced Settings:
	 Diameter of smallest tree cut Number of legacy trees per acre Minimum diameter of legacy trees
	Prescribed Burn - A wildfire set intentionally for purposes of forest management, farming, prairie restoration or greenhouse gas abatement (source: Wikipedia).
	Advanced Settings:
	 Wind speed (mph) at 20 feet above the vegetation Moisture level (1=Very Dry, 2=Dry, 3=Moist, 4=Wet) Temperature (F) Mortality Code (0=Turn off FFE mortality, 1= FFE estimates mortality Percentage of stand area burned (%) Season of fire (1=Early spring, 2=Before greenup, 3=After greenup (before fall), 4=Fall)
Run simulation on non-selected Stands	Checking this box runs the simulation on all of the stands in the input feature class, not just the selected ones.
EEMS Model	A list of available EEMS models to run on the output values generated by FVS. The output values from the last year of the simulation will be used in the EEMS model.
	Note that you must be sure to check the "Output Fields To Join" boxes corresponding to the inputs fields used by the READ commands in the EEMS model.
	Two sample EEMS models are available by default. Additional EEMS models can be developed and added to the Treatment Planner. The only requirement is that they are configured to make use of one or more of the "Output Fields to Join" variables generated by FVS.
EEMS Model Output Feature Class	The path to the EEMS model output feature class.

IV. TREATMENT PLANNER TUTORIAL

4.1 Overview

The tutorial below will demonstrate how to run the Treatment Planner using four stands located just outside the community of Shaver Lake California in the mixed conifer forest of the Southern Sierra Nevada Mountains. In this example, we will play the role of a forest manager interested in determining what the severe fire risk in this area will be in 10 years under two different management alternatives:

- 1. No Action Alternative (no treatments/management actions)
- 2. Thinning Treatment (A management plan that involves thinning a high risk stand on year 5)

After each simulation, we will examine the predicted effects of each of these management alternatives in order to help us select a management strategy that will be most effective in reducing the severe fire risk in this area.

4.2 Disclaimer

The data and models used in this tutorial are intended for demonstration purposes only and have not been vetted for accuracy. Consequently, the outputs generated from the simulations performed in this tutorial will not necessarily reflect real-world conditions and should not be used for purposes other than testing and training.

4.3 Preparation

- 1. If you haven't already, extract the contents of the Treatment_Planner_BETA.zip file to a desired location on your local hard drive.
- 2. Open the Tutorial MXD located in the MXD folder (Treatment_Planner_Tutorial_Map.mxd).
- 3. Each of the four stands in the Shaver Lake Forest Stands layer (shown below) has a corresponding record in the FVS_StandInit table in the ShaverLake.accdb FVS database. The values in the STAND_ID field (shown as labels below) are what allows the Treatment Planner to associate each of these polygons with a record in the FVS_StandInit table. The FVS_TreeInit table in the FVS database contains all the information about the trees located within each of these stands.



While we will only be examining four stands in this tutorial, the FVS_StandInit table contains records for several additional stands present in this area. Some of these stands also have corresponding polygons, which can be found in the Shaver_Lake_Forest_Stands_All feature class.

- 4. Optional: Open up the sample FVS database in Microsoft Access and examine the FVS_StandInit table and the FVS_TreeInit table. The FVS_TreeInit table contains a record for each tree (or collection of similar trees) located within each of the stands in the FVS_StandInit table. The STAND_ID field indicates which stand each of these trees is located within. Other fields in the FVS_TreeInit table include the species code, DBH, height, and crown ratio. Additional information regarding the data in the FVS_TreeInit table can be found in the FVS Documentation.
- 5. Close Microsoft Access if it is open.
- 6. **Optional:** Open up and examine the Severe Fire Risk EEMS model in the EEMS_Models toolbox. This is the model that the Treatment Planner will use to predict the severe fire risk in each of our stands x years into the future.

There are two main branches to this model (show below in Figure 4):

The left-hand branch (Topography is conducive to Fire) is based on topographic properties that don't change over time (Southwestness, Solar Insulation, and Slope). These values have been precalculated in the input stands feature class we'll be using in the tutorial. These are not values that the Treatment Planner will generate, so if you intend to run this model on your own stands, these values would first need to be calculated.

The right-hand branch (Structure is Conducive to Fire) is based on the outputs generated by FVS x years into the future (Basal Area, Tree Density, Stand Density Index, and Crown Competition).



Figure 4. A graphical representation of The Severe Fire Risk Model included with the Treatment Planner

Please refer to section V of this document for information on how to include your own EEMS models in the Treatment Planner.

4.4 Scenario 1: No Action Alternative

Once the preparation steps above have been completed, you can proceed with the simulation below which will determine what the severe fire risk will be in 10 years, for each stand, under the no action alternative (i.e., if no treatments are performed).

- 1. In the Catalog Window in ArcMap, locate the Treatment Planner Toolbox, and double click the Run Simulation tool contained within it.
- 2. Drag the Shaver Lake Forest Stands layer over to the Forest Stands Layer input field.
- Browse to the following FVS Database if the path isn't already entered in: <Local Treatment Planner Path>\Data\Inputs\FVS_Databases\ShaverLake.accdb
- 4. Enter in 10 for the **Number of Years to Simulate**.
- 5. For the checkbox items in the **Output Fields to Join** list, click **Select All**. For each output field that is selected, the final value for the last year of the simulation will be joined to the output feature class.
- 6. Since we are simulating a no action alternative, we will leave the **Management Actions** options blank.
- 7. Under **Post-Processing Options** -> select **Severe Fire Risk** from the list of EEMS Models that appear dropdown menu.
- 8. Leave the EEMS Model Output Feature Class as-is.
- 9. Click Ok.
- 10. After the tool runs through an initialization process, you'll notice that the tool dialog box will display the output data generated by FVS for each stand in the stands layer:

npleted	ł																	
npieceo																		Close
																		<< Det
																		- COCC
Close th	his dialog v	vhen o	complete	ed succ	essfully													
Start	ting Si	mula	ation	ı														
	D ID :0																	
	ting FV ing FVS		eywor	d Fi	1e													
xummi	ing rv5	••••																
			Т	E FV	S VAF	TANT -	- RV:2	201903	07									
	STA	ND =	= 051	5523	36002	23		M	ANAGEMI	ENT (CODE	= NO	NE					
	STA	ND =	= 051	.5523	36002		nd 0515		ANAGEMI 0023	ENT (CODE	= NO	NE					
	STA	ND =				Star		52336					NE					
			SUMM	IARY	STATI	Star ISTICS	(BASEI	52336 O ON T	0023 OTAL SI	TAND	AREA	4) 						
			SUMM	IARY	STATI	Star ISTICS PERIOD	(BASEI REN	52336 O ON T 	0023 OTAL SI 	TAND Al	AREA	A) TREA	TMEN					
	STAR	T 01	SUMM F SIM	IARY IULAT	STATI ION H	Star ISTICS PERIOD	(BASEI REN	52336 O ON T 10VALS	0023 OTAL 51 /ACRE	TAND Al	AREA) TREA	TMEN	CU I	т			
	STAR	T OI	SUMM F SIM	IARY IULAT TOP	STATI ION H	Star ISTICS PERIOD TOTAL	(BASEI REN TREES	52336) ON T 10VALS TOTAL	0023 OTAL 51 /ACRE MERCH	TAND 	AREA FTER	A) TREA TOP	TMEN1	CU I PER	T YR			
YEAR	STAR TREES /ACRE	T 01 BA	SUMM F SIM	IARY IULAT TOP HT	STATI ION E QMD	Star ISTICS PERIOD TOTAL CU FT	(BASEI REM TREES /ACRE	OVALS TOTAL CU FT	0023 OTAL SI /ACRE MERCH BD FT	AI	AREA FTER SDI	TREA TOP HT	QMD	CU I PER ACC	T YR MOR 			
YEAR 2017	STAR TREES /ACRE 170	EA 40	SUMM F SIM SDI 87	IARY IULAT TOP HT 39	STATI ION E QMD 6.6	Star ISTICS PERIOD TOTAL CU FT 635	(BASEI REN TREES /ACRE 0	52336) ON T MOVALS TOTAL CU FT 0	0023 OTAL SI /ACRE MERCH BD FT 0	EAND Al BA 40	AREA FTER SDI 87	1) TREA TOP HT 39	 6.6	CU I PER ACC 18	YR MOR 4			
YEAR 2017 2018	STAR TREES /ACRE 170 166	BA 40 40	SUMM F SIM SDI 87 87	IARY IULAT TOP HT 39 40	STATI ION E QMD 6.6 6.7	Star ISTICS PERIOD TOTAL CU FT 635 649	(BASEI REN TREES /ACRE 0 0	52336 0 ON T 10VALS TOTAL CU FT 0 0	0023 OTAL SI /ACRE MERCH BD FT 0 0	EAND Al BA 40 40	ARE# FTER SDI 87 87	TREA TOP HT 39 40	 QMD 6.6 6.7	CU I PER ACC 18	T YR MOR 			
YEAR 2017 2018 2019	STAR TREES /ACRE 170 166 163	BA 40 40 41	SUMM F SIM SDI 87 87 87	IARY IULAT TOP HT 39 40 40	2MD 6.6 6.7 6.8	Star ISTICS PERIOD TOTAL CU FT 635 649 663	(BASEI REN TREES /ACRE 0 0 0	52336 0 ON T 00VALS TOTAL CU FT 0 0 0 0	0023 OTAL SI /ACRE MERCH BD FT 0 0 0	AI AI BA 40 40 41	ARE# FTER SDI 87 87 87	TREA TOP HT 39 40 40 40	 6.6	CU 1 PER ACC 18 18 18	YR MOR 4 4			
YEAR 2017 2018 2019 2020	STAR TREES /ACRE 170 166 163	BA 40 40 41 41	SUMM F SIM SDI 87 87 87 87	IARY IULAT TOP HT 39 40 40 41	2MD 0.6 6.6 6.7 6.8 6.9	Star ISTICS PERIOD TOTAL CU FT 635 649 663 677	(BASEI REN TREES /ACRE 0 0 0 0 0	52336 0 ON T 00VALS TOTAL CU FT 0 0 0 0	0023 OTAL SI /ACRE MERCH BD FT 0 0 0 0	BA 40 41 41	ARE# FTER SDI 87 87 87 87	TREA TOP HT 39 40 40 41	QMD 6.6 6.7 6.8 6.9	CU I PER ACC 18 18 18 18 17	T YR MOR 4 4 4			
YEAR	STAR TREES /ACRE 170 166 163 159	BA 40 40 41 41 41	SUMM F SIM SDI 87 87 87 87 87 87	IARY IULAT TOP HT 39 40 40 41 41	2MD 6.6 6.7 6.8 6.9 7.0	Star ISTICS PERIOD TOTAL CU FT 635 649 663 677 690	(BASEI REN TREES /ACRE 0 0 0 0 0 0 0 0	552336 0 ON T 10VALS TOTAL CU FT 0 0 0 0 0 0	0023 OTAL SI /ACRE MERCH BD FT 0 0 0 0 0 0 0 0	AND AI BA 40 40 41 41 41	ARE# FTER SDI 87 87 87 87 87	<pre>X) TREA TOP HT 39 40 40 41 41</pre>	QMD 6.6 6.7 6.8 6.9 7.0	CU I PER ACC 18 18 18 18 17 18	T YR MOR 4 4 4 4			
YEAR 2017 2018 2019 2020 2021	STAR TREES /ACRE 170 166 163 159 156 153	BA 40 40 41 41 41 42	SUMM F SIM SDI 87 87 87 87 87 87 88	IARY IULAT TOP HT 39 40 40 41 41 41	2MD 6.6 6.7 6.8 6.9 7.0 7.1	Star ISTICS PERIOD TOTAL CU FT 635 649 663 677 690 704	(BASEI 	552336 0 ON T 00VALS TOTAL CU FT 0 0 0 0 0 0 0 0 0	0023 OTAL ST /ACRE MERCH BD FT 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	AND AI BA 40 40 41 41 41 42	ARE# FTER SDI 87 87 87 87 87 87 88	A) TREA TOP HT 39 40 40 41 41 41	QMD 6.6 6.7 6.8 6.9 7.0 7.1	CU I PER ACC 18 18 18 17 18 19	T YR MOR 4 4 4 4 4			
YEAR 2017 2018 2019 2020 2021 2022	STAR TREES /ACRE 1700 166 163 159 156 153 150	BA 40 40 41 41 41 42 42	SUMM F SIM SDI 87 87 87 87 87 87 88 88 88	IARY IULAT TOP HT 39 40 40 41 41 41 41 42	STATI ION E 0MD 6.6 6.7 6.8 6.9 7.0 7.1 7.2	Star ISTICS PERIOD TOTAL CU FT 635 649 663 677 690 704 718	(BASEI 	552336 0 ON T 40VALS TOTAL CU FT 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	0023 OTAL ST /ACRE MERCH BD FT 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	AND AI BA 40 40 41 41 41 42 42	AREZ FTER SDI 87 87 87 87 87 87 88 88 88	A) TREA TOP HT 39 40 40 41 41 41 41 41	QMD 6.6 6.7 6.8 6.9 7.0 7.1	CU I PER ACC 18 18 18 18 17 18 19 18	T YR MOR 4 4 4 4 5			
YEAR 2017 2018 2019 2020 2021 2022 2022 2023	STAR TREES /ACRE 1700 166 163 159 156 153 150	BA 40 40 41 41 41 42 42 42	SUMM F SIM SDI 87 87 87 87 87 87 88 88 88 88	IARY IULAT TOP HT 39 40 40 41 41 41 41 42 42	STATI ION E 0MD 6.6 6.7 6.8 6.9 7.0 7.1 7.2 7.2	Star ISTICS PERIOD TOTAL CU FT 635 649 663 677 690 704 718 732	(BASEI 	552336 0 ON T 40VALS TOTAL CU FT 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	0023 OTAL ST /ACRE MERCH BD FT 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	AND AI BA 40 40 41 41 41 42 42 42 42	ARE# FTER SDI 87 87 87 87 87 88 88 88 88 88	A) TREA TOP HT 39 40 40 41 41 41 41 42 42	QMD 6.6 6.7 6.8 6.9 7.0 7.1 7.2	CU 1 PER ACC 18 18 18 17 18 19 18 20	T YR MOR 4 4 4 4 5 5			
YEAR 2017 2018 2019 2020 2021 2022 2023 2023 2024	STAR TREES /ACRE 170 166 163 159 156 153 150 148 147 146	BA 40 40 41 41 41 42 42 42 43 43	SUMM F SIM SDI 87 87 87 87 87 87 88 88 88 88 88 88 88	IARY IULAT TOP HT 39 40 40 41 41 41 41 41 42 42 43 43	QMD 6.6 6.7 6.8 6.9 7.0 7.1 7.2 7.2 7.3 7.4	Star ISTICS PERIOD TOTAL CU FT 635 649 663 677 690 704 718 732	(BASEI REN TREES /ACRE 0 0 0 0 0 0 0 0 0 0 0 0 0	552336 0 ON T 40VALS TOTAL CU FT 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	0023 OTAL ST /ACRE MERCH BD FT 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	AND AI BA 40 40 41 41 41 42 42 42 42	AREA FTER SDI 87 87 87 87 87 87 87 88 88 88 88 88 88	TREA TOP HT 39 40 40 41 41 41 41 42 42 43	QMD 6.6 6.7 6.8 6.9 7.0 7.1 7.2 7.2	CU I PER ACC 18 18 18 17 18 19 18 20 18	T YR MOR 4 4 4 4 5 5 5			

What this is showing is change in forest conditions over time, within each stand, starting on year 0 (2017), and continuing through to year 10 (2027). The table below describes what each of these columns represents.

START OF SIMULATION PERIOD The simulation year TREES/ACRE Trees per acre (Tpa) is a count of the number of trees per acre. BA Basal area per acre (BA) describes the average amount of an acre (measured in square feet) occupied by the cross section of tree stems SDI Stand Density Index (SdI) is a relative measure of stand density that is based on the number of trees per unit area and diameter at breast height (DBH) of the tree of average basal area (source: Wikipedia). TOP HT Average dominant height (ToPHt) is the average height of the 40 largest diameter trees (source: FVS Manual). QMD Quadratic mean DBH (QMD) is the DBH of the tree of average basal area (source: FVS Manual). TOTAL CU FT Total cuft volume (CuFt) represents the volume of timber in cubic feet. REMOVALS/ACRE Trees per acre (Tpa) removed based on any management actions specified. TOTAL CU FT Total cuft volume (CuFt) removed based on any management actions specified. MERCH BD FT Merchantable cuft volume (CuFt) removed based on any management actions specified. AFTER TREATMENT GROWTH Basal area per acre (BA) growth following any management actions specified. SDI Stand Density Index (SdI) growth following any management actions specified.	Column	Description
TREES/ACRETrees per acre (Tpa) is a count of the number of trees per acre.BABasal area per acre (BA) describes the average amount of an acre (measured in square feet) occupied by the cross section of tree stemsSDIStand Density Index (Sdi) is a relative measure of stand density that is based on the number of trees per unit area and diameter at breast height (DBH) of the tree of average basal area (source: FVS Manual).TOP HTAverage dominant height (TopHt) is the average height of the 40 largest diameter trees (source: FVS Manual).QMDQuadratic mean DBH (QMD) is the DBH of the tree of average basal area (source: FVS manual).TOTAL CU FTTotal cuft volume (CuFt) represents the volume of timber in cubic feet.REMOVALS/ACRETrees per acre (Tpa) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.BABasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any management actions specified.	START OF SIMULATION PERIOD	
of trees per acre.BABasal area per acre (BA) describes the average amount of an acre (measured in square feet) occupied by the cross section of tree stemsSDIStand Density Index (Sdi) is a relative measure of stand density that is based on the number of trees per unit area and diameter at breast height (DBH) of the tree of average basal area (source: Wikipedia).TOP HTAverage dominant height (TopHt) is the average height of the 40 largest diameter trees (source: FVS Manual).QMDQuadratic mean DBH (QMD) is the DBH of the tree of average basal area (source: FVS manual).TOTAL CU FTTotal cuft volume (CuFt) represents the volume of timber in cubic feet.REMOVALS/ACRETrees per acre (Tpa) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.BABasal area per acre (BA) growth following any management actions specified.SDIStand cuff volume (CuFt) removed based on any management actions specified.AFTER TREATMENT GROWTHStand Density Index (Sdi) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any management actions specified.	YEAR	The simulation year
amount of an acre (measured in square feet) occupied by the cross section of tree stemsSDIStand Density Index (Sdi) is a relative measure of stand density that is based on the number of trees per unit area and diameter at breast height (DBH) of the tree of average basal area (source: Wikipedia).TOP HTAverage dominant height (TopHt) is the average height of the 40 largest diameter trees (source: FVS Manual).QMDQuadratic mean DBH (QMD) is the DBH of the tree of average basal area (source: FVS Manual).TOTAL CU FTTotal cuft volume (CuFt) represents the volume of timber in cubic feet.REMOVALS/ACRETrees per acre (Tpa) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.AFTER TREATMENT GROWTHBasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any	TREES/ACRE	
SDIoccupied by the cross section of tree stemsSDIStand Density Index (Sdi) is a relative measure of stand density that is based on the number of trees per unit area and diameter at breast height (DBH) of the tree of average basal area (source: Wikipedia).TOP HTAverage dominant height (TopHt) is the average height of the 40 largest diameter trees (source: FVS Manual).QMDQuadratic mean DBH (QMD) is the DBH of the tree of average basal area (source: FVS manual).TOTAL CU FTTotal cuft volume (CuFt) represents the volume of timber in cubic feet.REMOVALS/ACRETrees per acre (Tpa) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.AFTER TREATMENT GROWTHBasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any management actions specified.	ВА	Basal area per acre (BA) describes the average
SDIStand Density Index (Sdi) is a relative measure of stand density that is based on the number of trees per unit area and diameter at breast height (DBH) of the tree of average basal area (source: Wikipedia).TOP HTAverage dominant height (TopHt) is the average height of the 40 largest diameter trees (source: FVS Manual).QMDQuadratic mean DBH (QMD) is the DBH of the tree of average basal area (source: FVS manual).TOTAL CU FTTotal cuft volume (CuFt) represents the volume of timber in cubic feet.REMOVALS/ACRETrees per acre (Tpa) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.AFTER TREATMENT GROWTHBasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any management actions specified.		amount of an acre (measured in square feet)
of stand density that is based on the number of trees per unit area and diameter at breast height (DBH) of the tree of average basal area (source: Wikipedia).TOP HTAverage dominant height (TopHt) is the average height of the 40 largest diameter trees (source: FVS Manual).QMDQuadratic mean DBH (QMD) is the DBH of the tree of average basal area (source: FVS manual).TOTAL CU FTTotal cuft volume (CuFt) represents the volume of timber in cubic feet.REMOVALS/ACRETrees per acre (Tpa) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.TOTAL CU FTMerchantable cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.BABasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any management actions specified.		occupied by the cross section of tree stems
trees per unit area and diameter at breast height (DBH) of the tree of average basal area (source: Wikipedia).TOP HTAverage dominant height (TopHt) is the average height of the 40 largest diameter trees (source: FVS Manual).QMDQuadratic mean DBH (QMD) is the DBH of the tree of average basal area (source: FVS manual).TOTAL CU FTTotal cuft volume (CuFt) represents the volume of timber in cubic feet.REMOVALS/ACRETrees per acre (Tpa) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.BABasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any management actions specified.	SDI	
height (DBH) of the tree of average basal area (source: Wikipedia).TOP HTAverage dominant height (TopHt) is the average height of the 40 largest diameter trees (source: FVS Manual).QMDQuadratic mean DBH (QMD) is the DBH of the tree of average basal area (source: FVS manual).TOTAL CU FTTotal cuft volume (CuFt) represents the volume of timber in cubic feet.REMOVALS/ACRETrees per acre (Tpa) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.BABasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any management actions specified.		
Image: space in the initial in		·
TOP HTAverage dominant height (TopHt) is the average height of the 40 largest diameter trees (source: FVS Manual).QMDQuadratic mean DBH (QMD) is the DBH of the tree of average basal area (source: FVS manual).TOTAL CU FTTotal cuft volume (CuFt) represents the volume of timber in cubic feet.REMOVALS/ACRETrees per acre (Tpa) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.AFTER TREATMENT GROWTHBasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any		
(source: FVS Manual).QMDQuadratic mean DBH (QMD) is the DBH of the tree of average basal area (source: FVS manual).TOTAL CU FTTotal cuft volume (CuFt) represents the volume of timber in cubic feet.REMOVALS/ACRETrees per acre (Tpa) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.TOTAL CU FTMerchantable cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.BABasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any	TOP HT	
tree of average basal area (source: FVS manual).TOTAL CU FTTotal cuft volume (CuFt) represents the volume of timber in cubic feet.REMOVALS/ACRETrees per acre (Tpa) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.AFTER TREATMENT GROWTHBasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any		
manual).TOTAL CU FTTotal cuft volume (CuFt) represents the volume of timber in cubic feet.REMOVALS/ACRETrees per acre (Tpa) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.AFTER TREATMENT GROWTHBasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any	QMD	Quadratic mean DBH (QMD) is the DBH of the
volume of timber in cubic feet.REMOVALS/ACRETrees per acre (Tpa) removed based on any management actions specified.TREES/ACRETrees per acre (Tpa) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.AFTER TREATMENT GROWTHBasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any monagement actions specified.		
TREES/ACRETrees per acre (Tpa) removed based on any management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.AFTER TREATMENT GROWTHBasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any following any following any	TOTAL CU FT	
management actions specified.TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.AFTER TREATMENT GROWTHAFTER TREATMENT GROWTHBABasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any	REMOVALS/ACRE	
TOTAL CU FTTotal cuft volume (CuFt) removed based on any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.AFTER TREATMENT GROWTHAFTER TREATMENT GROWTHBABasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any	TREES/ACRE	Trees per acre (Tpa) removed based on any
any management actions specified.MERCH BD FTMerchantable cuft volume (CuFt) removed based on any management actions specified.AFTER TREATMENT GROWTHBasal area per acre (BA) growth following any management actions specified.BABasal area per acre (BA) growth following any management actions specified.SDIStand Density Index (Sdi) growth following any		management actions specified.
MERCH BD FT Merchantable cuft volume (CuFt) removed based on any management actions specified. AFTER TREATMENT GROWTH Basal area per acre (BA) growth following any management actions specified. BA Basal area per acre (BA) growth following any management actions specified. SDI Stand Density Index (Sdi) growth following any	TOTAL CU FT	Total cuft volume (CuFt) removed based on
AFTER TREATMENT GROWTH based on any management actions specified. BA Basal area per acre (BA) growth following any management actions specified. SDI Stand Density Index (Sdi) growth following any		any management actions specified.
AFTER TREATMENT GROWTH Basal area per acre (BA) growth following any management actions specified. SDI Stand Density Index (Sdi) growth following any	MERCH BD FT	Merchantable cuft volume (CuFt) removed
BA Basal area per acre (BA) growth following any management actions specified. SDI Stand Density Index (Sdi) growth following any		based on any management actions specified.
SDI Stand Density Index (Sdi) growth following any	AFTER TREATMENT GROWTH	
SDI Stand Density Index (Sdi) growth following any	ВА	Basal area per acre (BA) growth following any
		management actions specified.
management actions specified.	SDI	
		management actions specified.

ТОР НТ	Average dominant height (TopHt) following any management actions specified.
QMD	Quadratic mean DBH (QMD) following any management actions specified.
CUBIC FT PER YR	
ACC	Cubic Feet of Timber accumulated per year
MOR	Cubic Feet of Timber removed via mortality per year

11. After you've had a chance to examine the output of the tool dialog, click close and examine the output layer that was automatically added to the table of contents. You'll notice that the EEMS Model has determined that one of the stands (0515523360030) is expected to have a **VERY HIGH** risk of a severe fire in 10 years if no treatments are performed. If you look in the attribute table of the output, you'll notice that the value in the **High_Severe_Fire_Risk_Fz** field is 0.79 on a scale of -1 to +1. Moreover, it is surrounded by stands that are expected to have a **MODERATELY HIGH** severe fire risk.



4.5 Scenario 2: Single Thinning Treatment

In this example, we will conduct the same the analysis as above, except we will now perform a single thinning treatment on the stand that was determined to be at high risk under the no action alternative.

1. In ArcMap, uncheck the EEMS Output in the Table of Contents, and select the high risk stand in the original stands layer using the **Select Features** arrow (as shown below). Note

that it is possible to select multiple stands for treatment if desired. For this tutorial, however, we are only interested in applying a treatment to this single stand.



- 2. Click Geoprocessing Results Current Session Run Simulation. This is a shortcut that will open up the tool with the same parameters used in the last simulation.
- 3. Leave everything the same, but under Management Actions, select **Thin From Below**.
- 4. In the Year column, enter in 5 to specify that we would like to perform the treatment on the 5th year. Note that this parameter uses a 0 index starting value (so entering in a value of 0 would perform the treatment on the inventory year associated with the stand(s) in the FVS database).
- 5. Leave the "Run simulation on non-selected Stands" checked. This will force the simulation to run on all the stands, not just the stand(s) selected for treatment. However often for testing purposes, and/or when dealing with large FVS databases and evaluating multiple scenarios, it is quicker and more efficient to uncheck this box.
- 6. Expand the Post-Processing options to confirm that the **Severe Fire Risk** model is still selected.
- 7. Click Ok.
- 8. As the simulation is performed, the dialog box will again show the outputs generated by FVS. As it does this, notice what happens to the values under "REMOVALS/ACRES" field on year 5 in the stand that you selected for treatment (0515523360030). Because we specified a thinning treatment on year 5, these fields will now indicate the number of trees per acre removed, the total cubic board feet removed, and the total merchantable board feet removed by this treatment. The values under the START OF SIMULATION PERIOD have also changed in response to the thinning treatment. There are now fewer trees per acre, the basal area has decreased, the trees are now smaller on average, etc.

mpleter	d																Close << Details
- OICU	this dialog	-D 10															^
Kunn	ing FV: STI				VS VA 33600:		RV:2	М	ANAG		ENT (CODE	= N(ONE			
	STAI	RT O				ISTICS PERIOD		IOVALS	/ACR	E	AI	TER	TREA	ATMEN			-
	IKEES			TOP			IKEES	TOTAL	MER	СН			TOP		PER	IK	_
YEAR	/ACRE		SDI	HT	QMD	CU FT	/ACRE	CU FT	BD	FT		SDI	HT	QMD	ACC	MOR	
2017	750	172	374	93	6.5	7881	0	0		0	172	374	93	6.5	61	25	
2018		173				7917					173		93			25	
2019		174			6.9 7.1		0	0			174 174		93 94	6.9 7.1		26 27	
2020						8033	0	0		-	175		94			28	
2022			359			8067		4393	242	-							-
2023	73	60	101	19	12.3	3653	0	0		0	0	101	19	12.3	11	1	
2024			103			3662	0	0	▲					11.8			
2025		60 60	104		11.4	3673 3683	0	0		0				11.4		1	
2026	90		106		10.8	3693	0	0		0				10.8	0	0	
	D ID : (ting F					▲							↑				- 1
	ing FV:		-1		_												
				শৰ ৰ	. т	hese v	alues ł	nave c	han	ge	d to	refle	ect				~
				B. B./	0					•					-		
	ome	of +	had	ha	۲r ر	ne thin	ning ti	reatm	ent	pe	rror	mea	on		nor	+ ~ ~	year

- a. There are now fewer trees per acre (TREES/ACRE).
- b. The Basal Area per acre (BA) has decreased.
- c. The Stand Density Index (SDI) has decreased.
- d. The average height of the 40 largest diameter trees (TOP HT) has decreased.
- e. The total cubic feet has decreased.
- 9. After you've had a chance to examine the output in the tool dialog, click close and examine the output layer that was automatically added to the table of contents. You'll notice that the stand that previously had a high fire risk in 10 years under the no action alternative now has a **MODERATELY LOW** severe fire risk because of the treatment we performed. If you examine the attribute table, you'll see that the value in the **High_Severe_Fire_Risk_Fz** field for this stand has dropped significantly from 0.79 to -0.36.

4.6 Conclusion

In this tutorial, we have demonstrated how the Treatment Planner can be used to help land managers evaluate the effects of different management alternatives on a forested landscape. We tested two alternatives and discovered that under the No Action Alternative, one of the stands just outside the community of Shaver Lake would have a VERY HIGH risk for a high severity fire in 10 years. We then repeated the simulation with a thinning treatment performed on year 5 and discovered that this reduced the Severe Fire Risk of this stand from VERY HIGH (0.79) to MODERATELY LOW (-0.36), suggesting that this would be the preferred management strategy to implement on the ground.

At this point it is important to note that the output risk value will be highly sensitive to the TRUE and FALSE thresholds used in the Severe Fire Risk EEMS model. Most of the thresholds in this model were set at 1STD from the mean (based on the output from an initial simulation using all the stands in the Shaver_Lake_Forest_Stands_All feature class. Users wanting to run this model in a different study area may want to adjust these thresholds.

This concludes the tutorial. At this point you are encouraged to experiment with different scenarios. For example, try performing the treatment on a different year. If the stand in question currently has a high fire risk, it might make more sense to perform the treatment during the current year (year 0) if feasible. How does that affect the severe fire risk in this stand in 10 years? Try experimenting with different management actions, and perhaps multiple management actions on different years. Also notice that each management action has an "Advanced Settings" parameter that will allow you to fine tune each management action.

Finally, remember it is important to look not only at the classified output (High, Very High, etc.), but also at the continuous values generated in the **High_Severe_Fire_Risk_Fz** field.

V. ADDING CUSTOM EEMS MODELS

*Note: This section assumes that users are already familiar with EEMS and have experience building EEMS models. This manual does not provide instructions on how to create EEMS models. To learn more about EEMS and the process of building EEMS models, please refer to the EEMS Manual.

The Treatment Planner comes pre-packaged with two sample EEMS models. If you completed the tutorial in the previous section, you are already familiar with the Severe Fire Risk model. In this section, we will see how advanced users can develop and include their own EEMS models in the Treatment Planner. These models could be designed to calculate any variable of interest (e.g., *fisher habitat quality* or *bark beetle infestation predictions*). They just need to be added to the EEMS_Models toolbox, configured to make use of one or more of the outputs variables generated by FVS (shown below), and added to the Run Simulation tool.

Output variables generated by FVS

- I. Age (Stand Age)
- II. Tpa (Trees per acre)
- III. BA (Basal area per acre)
- IV. Sdi (Stand Density Index)
- V. CCF (Crown competition factor)
- VI. TopHt (Average dominant height)
- VII. QMD (Quadratic mean DBH)
- VIII. MCuFt (Merchantable cuft volume)
- IX. ForTyp (Forest Cover Type)
- X. SizeCls (Stand Size Class)

To use the variables above in a custom EEMS model, you simply need to add them to an **EEMS Read** command using the following form:

<FVS_Variable_Name>_%Simulation Year%

For example, if you would like your EEMS model to use the **BA** variable generated by FVS (Basal area per acre), you would enter the following into the Input Field of the EEMS Read command:

BA_%Simulation Year%

%Simulation Year% is a variable that will be populated automatically using the final year of the simulation (e.g., 2020).

In addition to the FVS variables, your EEMS model can also make use of static variables that do not change with each simulated timestep (for example slope, or elevation). These fields just need to be pre-calculated and included in the input stands feature class, and can then be used in an EEMS Read command as they normally would.

💐 EEMS Read	_		×
EEMS Input Table Input Feature Class			6
Input Field BA_%Simulation Year%			~
EEMS Command File %EEMS Command File Path%			
¥ Metadata			
			~
OK Cancel Environment	s	Show H	elp >>

Before developing your own EEMS models for use in the Treatment Planner, it is recommended that you first open up and examine one of the sample EEMS models to use as a reference. In particular, examine the EEMS Read commands to see how they conform to the rules described above.

Making Your Models Transportable

In order to ensure that the models you develop for the Treatment Planner are transportable – i.e., that they can be used if/when the Treatment Planner folder is moved to a new location within your file structure (or provided to another user) – it is recommended that you perform the following steps:

- 1. Rename the "EEMS Input Table Path" Bubble to something else (e.g., "Not Used")
- 2. Create a new string variable called EEMS Input Table Path.
- 3. Double click the **EEMS Input Table Path** variable you created above and enter in the name that appears in the bubble associated with your input feature class, between percentage signs. For example, if the name on your input feature class bubble is the default "Input Feature Class Path", then you would simply enter in **%Input Feature Class Path%**, as shown below.



If you don't perform the steps above, you will just to need to make sure that you right click and run the "**EEMS Model Initialize**" tool in your model anytime the Treatment Planner folder is moved to a new location. Failure to perform at least one of these options will likely generate the following traceback error:

```
Traceback (most recent call last):
    File "<string>", line 450, in execute
    File "C:\temp\tp\5\Treatment_Planner_BETA\EEMS\EEMS_Models.tbx", line 26, in
    SevereFireRisk
        šC_9N_@$ExecuteError: Failed to execute. Parameters are not valid.
Traceback (most recent call last):
    File "<string>", line 492, in updateParameters
    File "c:\program files (x86)\arcgis\desktop10.6\arcpy\arcpy\__init__.py", line 1138, in
    ListFields
        return gp.listFields(dataset, wild_card, field_type)
    File "c:\program files (x86)\arcgis\desktop10.6\arcpy\arcpy\geoprocessing\_base.py", line
    346, in listFields
        self.gp.ListFields(*gp_fixargs(args, True)))
IOError: "%EEMS Input Table Path%" does not exist
```

Adding Your Custom EEMS model To the Treatment Planner

After you have developed an EEMS model for use in the Treatment Planner (within the **EEMS_Models** toolbox), right click on your model and select **Properties**. On the **General** tab, give your model a **Name**. The model **Name** may be different from the model **Label** which is what you see in the catalog window. You will need to reference the model **Name** in the steps below.

Before performing the steps below, it is highly recommended that you make a backup copy of the **Treatment_Planner.tbx** toolbox as you will need to make edits to it.

- After you have developed your model following the guidelines above, open up the Treatment Planner Toolbox (Treatment_Planner.pyt) in a text editor or a Python IDE so that we can add the model to the Run Simulation Tool.
- 2. First, you will need to indicate the name you would like to appear when selecting your custom EEMS model from the model dropdown list. To do this, add a name to the param6 filter list, replacing <new model dropdown name> with a name of your choosing. You can use any name here you like it does not have to correspond to the actual name of the model.

param6.filter.list = ["Severe Fire Risk", "Thinning Assessment", "<new model dropdown
name>"]]

3. Next, add the block of code below to the EEMS Models section of the Treatment_Planner.pyt file (located at the bottom of the file), replacing <new model dropdown name> with the dropdown name you decided on above, and replacing <EEMS model name> with the name that appears in the Name field on the General Tab of your EEMS Model. As an optional step, if you have a layer file (.lyr) that you have created ahead of time that is configured to symbolize your model output based on the final output field, you can put that layer file in the Data\Outputs\lyr folder and add the third line, replacing <layer file name> with the name of your layer file.

if eems_model == "<new model dropdown name>":
 arcpy.<EEMS model name>_EEMSModels(last_year, input_stands_path, eems_command_file)
 eems_lyr_file = eems_lyr_dir + "<layer file name>.lyr" #optional line

4. Finally, save the Treatment_Planner.pyt file, and Right Click -> Refresh the Treatment_Planner.pyt file in the Catalog Window. When you double click the Run Simulation tool, you should now see your EEMS Model listed in the EEMS Model dropdown.

REFERENCES CITED

Seymour, Robert. (2013). User's Guide to the Forest Vegetation Simulator (FVS) and Suppose Interface.

Sheehan, T. and Gough, M. (2016) A platform-independent fuzzy logic modeling framework for environmental decision support. Ecological Informatics. 34:92-101